

Products: CAM520 Pro

Firmware Version: 0.0.1004.36

Published Date: October 26, 2020

Copyright © 2019

Copyright Notice

This publication, including all photographs, illustrations and software, is protected under international copyright laws, with all rights reserved. Neither this manual, nor any of the material contained herein, may be reproduced without written consent of the author.

Disclaimer

The information in this document is subject to change without notice. The manufacturer makes no representations or warranties with respect to the contents hereof and specifically disclaim any implied warranties of merchantability or fitness for any particular purpose. The manufacturer reserves the right to revise this publication and to make changes from time to time in the content hereof without obligation of the manufacturer to notify any person of such revision or changes.

Limitations of Liability

UNDER NO CIRCUMSTANCES SHALL AVER BE LIABLE FOR DAMAGES OF ANY CHARACTER (E.G. DAMAGES FOR LOSS OF PROFIT, SOFTWARE RESTORATION, WORK STOPPAGE, LOSS OF SAVED DATA OR ANY OTHER COMMERCIAL DAMAGES OR LOSSES) RESULTING FROM THE APPLICATION OR IMPROPER USE OF THE AVER PRODUCT OR FAILURE OF THE PRODUCT, EVEN IF AVER IS INFORMED OF THE POSSIBILITY OF SUCH DAMAGES. FURTHERMORE, AVER WILL NOT BE LIABLE FOR THIRD-PARTY CLAIMS AGAINST CUSTOMER FOR LOSSES OR DAMAGES. AVER WILL IN NO EVENT BE LIABLE FOR ANY DAMAGES IN EXCESS OF THE AMOUNT AVER RECEIVED FROM THE END-USER FOR THE PRODUCT. **Content**

Revision History and System Requirement 2
Important Notice
New Features 4
Problems Fixed
Known Issues







Revision History and System Requirement

Firmware Version	Region	Date	Model
0.0.1004.36	WW	October 26, 2020	CAM520Pro
0.0.1004.30	WW	August 13, 2020	CAM520Pro
0.0.1004.28	WW	August 3, 2020	CAM520Pro
0.0.1004.18	WW	June 30, 2020	CAM520Pro
0.0.1000.82	WW	April 20, 2020	CAM520Pro
0.0.1000.78	WW	March 26, 2020	CAM520Pro/VC520Pro
0.0.1000.70	WW	JAN. 06, 2020	CAM520Pro/VC520Pro
0.0.1000.52	WW	DEC. 20, 2019	CAM520Pro/VC520Pro





Important Notice

- 1. PTZApp should be upgraded to v. 1.4.1087.90 (MAC); v. 1.4.1112.116 (Windows) to get full functions.
- 2. Smart frame uses face detection technology; please face the camera to ensure the detection accuracy. Side facial profiles are not detectable..
- 3. The smart frame detection distance is up to 6 meters. If more than 6 meters, the accuracy may drop.
- 4. H.264 IP video streaming supports Windows 7 &10. (not supports Windows 8.1)
- 5. During system upgrade, please DON'T turn off the power for any reasons.





New Features

Firmware Version	New Features				
0.0.1004.36	1. RS232 port: support Visca reboot command				
	2. Microsoft teams MTR: While connecting CAM520 Pro to Teams MTR system, the				
	RS232/IP stream/HDMI port will be disabled automatically. Users can enable it again via				
	PTZApp setting.				
0.0.1004.30	N/A				
0.0.1004.28	1. Image settings:				
	Original: When unplugging adapt	tor or rebooting, the image settings and WDR will be set			
	back to default value.				
	New: All the image settings and	WDR will be retained after unplugging adaptor or			
	rebooting.				
0.0.1004.18	1. Add SmartFrame preset point	function.			
	Original: Camera always goes ba	ack to central position to capture all participants and			
	zoom in.				
	New: Users can choose the prefe	erred preset point direction and camera will capture all			
	participants based on the appoin	ted preset point			
	1Â1	Vo			
	PTZ	Settings Diagnostic Utility			
	- -				
	Mirror	Off 🔹			
	ADDR	01			
	Protocol	VISCA			
	Baud Rate	9600			
	Tracking mode	Manual frame			
	SmartFrame preset point	Default(central of the screen) ▼			
	On Screen Menu	Preset 0			
	Auto Focus	Preset 1 Preset 2			
	Factory Default	Preset 3 Preset 4			
	T actory Deraut	Preset 5 Preset 6			
		Preset 7 Preset 8			
	PTZApp should be upgraded to v. 1.4.1087.90 (MAC); v. 1.4.1112.116 (Windows) to				
	 P12App should be upgraded to V. 1.4.1087.90 (MAC); V. 1.4.1112.116 (Windows) to get full functions 2. IP webpage: H.264 Profile setting adds.two options: H.264 Baseline Profile/ High profile 3. VISCA command adds power on/ off 				



	1	
0.0.1000.82	1.	Change camera zoom-in mechanism to be compatible with VeeMed
		software.
	2.	Change Webpage idle rule:
		Original: If there is no request on webpage, users will be logged out after
		30mins
		New: If there is no request on webpage, users will be logged out after 4 hrs
	3.	Change Webpage in use rule:
		Original: When webpage is in use for 2 hrs, users have to press resume
		button to continue the usage. Otherwise, they will be logged out.
		New: Remove this rule.
	4.	Webpage preset function: Users can edit the name of each preset point.
0.0.1000.78	5.	Change Webpage login process to enhance security mechanism.
	6.	Improve JP language translation on Webpage
	7.	Add RTMP on/off hotkey on number 8 on remote controller.
0.0.1000.70	8.	Revised Japanese language on both IP webpage and HDMI out OSD.
	9.	Improved auto frame performance up to 6 meters far.



Problems Fixed

Firmware Version	Problem Fixed
0.0.1004.36	N/A
0.0.1004.30	1. Fix bugs while connecting with MAC system: Some camera settings will be return to
	default while connecting with MAC.
0.0.1004.28	1. Fix remote control randomly abnormal issue
	2. Fix FW update randomly failure issue
0.0.1004.18	N/A
0.0.1000.82	1. Fixed bugs on remote control
0.0.1000.78	1. Fixed some bugs on speakerphone cascade.
0.0.1000.70	1. Fixed some bugs on HDMI functions.
0.0.1000.52	1. Fix RTMP streaming uploading to YouTube.
	Notice: Please don't change resolution setting while streaming is uploading.





Known Issues

Firmware Version	Problem Fixed
0.0.1004.36	N/A
0.0.1004.30	N/A
0.0.1004.28	N/A
0.0.1004.18	N/A
0.0.1000.82	N/A
0.0.1000.78	Audio streaming function for RTMP/RTSP is still not available.
0.0.1000.70	N/A
0.0.1000.52	After changing NTP time zone, the system will take 40 seconds to change to the
	corresponding time. This issue will be fixed in next FW release.

